Role of Environmental Monitoring Programs in Food Safety Program

Aaron M. Pleitner, Ph.D.
Food Safety Net Services
Tortilla Industry Association Annual Convention
June 2nd 2018



Introduction

- Culture of Food Safety
 - Rapidly accelerated in recent years
 - Increase in regulatory guidelines
 - Holistic management approach
 - Development of testing methodologies and tools
 - Molecular assays
 - Rapid TAT/response
 - Decrease incubation times
 - Typing methods (e.g. Whole genome sequencing)
 - Facility mapping and production windows



Approaches to Testing


- Holistic approach to Food Safety
 - Preventive controls to monitor:
 - · Supply chain
 - Finished product
 - Environment
 - Pre- and post-operation
 - Cleaning and sanitization
 - Intermittent
 - Broad ranging throughout facility
 - Frequency
 - Traffic flow
 - Plant design








- Procedural Considerations
 - Aseptic technique and GMP/GLPs
 - Use of gloves/provided gloves
 - · Washing of hands and forearms
 - Opening and closing of sample bags
 - Sampling area
 - 10cm² (4 in²), 1 ft², entire area of harborage/niche site, drain
 - This can effect what type of sampling apparatus is used
 - Sampling technique
 - For specific areas, 10 drags vertically followed by 10 drags horizontally
 - · Coverage of drain area
 - Vigorous swabbing around harborage/niche sites due to biofilm or strong adhesion to area
 - Type of hydration buffer for (a) neutralization, (b) type of sampling apparatus and (c) type of facility




















- Guidance provided by USDA FSIS for Listeria Control Programs
 https://www.fsis.usda.gov/wps/wcm/connect/259fcaf4-ce2b-4ba1-8140-da873243040f/Chapter 3 Controlling LM RTE guideline 0912.pdf?MOD=AJPERES
- Guidance provided by FDA for Control of Listeria in RTE
 - https://www.fda.gov/downloads/Food/GuidanceRegulation/Guidance
 DocumentsRegulatoryInformation/UCM535981.pdf
- Environmental Sampling for Poultry House in Section A
 - https://www.fda.gov/Food/FoodScienceResearch/LaboratoryMethods/ /ucm114716.htm



- Assessment and tracking of manufacturing site microbial fingerprint
 - Insight:
 - Hygienic state
 - Effectiveness of cleaning and sanitation efforts
 - Effect of traffic flow
 - · Effect of plant design
- Determination of testing sites
 - Zones:
 - Zone 1 Food contact surface (FCS)
 - Zone 2 Non-food contact surfaces (NFCS) directly adjacent to FCS
 - Zone 3 NFCS that are not adjacent to FCS but pose a threat to contamination in post-processing areas
 - Zone 4 NFCS that are remote from post-processing areas



Environmental Sampling Zones





- Implementation of environmental sampling plan
 - Identification of zones and testing sites
 - Increased testing frequency to begin with
 - Development of baseline microflora levels
 - Baseline allows for timeline and historical comparison
 - Swabbing of locations with sponge/cotton swab with hydration solution
 - Sanitizer residue has an effect on recovery
 - Appropriate hydration buffer solution necessary¹
 - Dey-Engley (D/E), Neutralizing Buffer (NB), Letheen Broth (LE), Buffered Peptone Water (BPW), etc.



- Testing targets
 - Indicator organisms
 - Aerobic plate count/Total plate count
 - Yeast/Mold
 - Enterobacteriaceae (EB)
 - Listeria spp.1
 - Listeria innocua
 - Listeria grayi
 - Listeria welshimeri
 - Listeria seeligeri
 - Target pathogens
 - Salmonella



- Testing methodologies
 - Surface sampling using either sponge, spongesicle or cotton swabs to specific surface area
 - Indicator organisms
 - Culture based methods (Quantitative)
 - Molecular based assay for Listeria (Qualitative Presence/Absence)
 - Target pathogens
 - Molecular and culture based assays
 - Enzyme-linked fluorescent immunoassay
 - Gene targets unique to target
 - More rapid than culture based qualitative methods
 - USDA MLG or FDA BAM culture based methodologies



- Testing methodology results
 - Quantitative method provides overall general population in the surface area samples (CFU/mL, CFU/g, CFU/cm²)
 - Qualitative method provides presence/absence of target bacteria
 - Stages to positive include:
 - Potential positive
 - Presumptive positive
 - Confirmed positive
 - Negative
 - False positive




- Further suggested steps:
 - Quantitative indicator organisms increase suggest increasing cleaning/sanitation interventions and intensified sampling
 - Qualitative method identifies either target indicator organism or presence of pathogen of concern
 - Suggested to halt production, deep clean, place product on hold
 - Typing of isolates from positive results determine if same species and possibly strain is tracking throughout facility/harboring at specific site
 - Intensified sampling to identify source¹
 - Rotation of sanitizer and cleaning agents
 - Biofilm identification



- Historical data collection and facility mapping
 - Defining of baseline, comparison with employee traffic flow, implementation of new GMPs, SSOPs, introduction of new vendors
 - Further typing of bacterial isolates
 - Pulsed-field gel electrophoresis
 - Whole genome sequencing
 - VITEK



Historical data collection and facility mapping



- Location examples:
 - Employee smocks/boots
 - Equipment surfaces
 - Floor locations
 - Drains
 - Doorways
 - Refrigerated storage
 - Carts
 - Breakroom
 - Drains




Air Sampling

- Place of an open plate in processing environment
- Use of sampling equipment
- Considerations
 - Room placement
 - Airflow in area
 - Traffic flow in area
 - Time during production
 - Velocity of collection translates to volume of air tested











Conclusions

- Sampling procedures and considerations are pivotal
- Environmental monitoring program is dependent on:
 - Identification of sites
 - Size and traffic of facility
 - Frequency and type of testing
- Environmental monitoring programs provide heartbeat of microbial presence
- Environmental monitoring programs and follow-up steps can provide insight into route of introduction and transmission and harborage points



Questions?



Appendix Slides



Culture Based for Qualitative and Quantitative Methods

- FDA Bacteriological Analytical Manual (BAM)
 - Chapter 3 for APC
 - Chapter 4A for Diarrheagenic Escherichia coli
 - Chapter 5 for Salmonella
 - Chapter 10 for Listeria monocytogenes
- USDA Microbiological Laboratory Guidebook (MLG)
 - 3.02 Sanitary Indicators
 - 4.09 for Salmonella
 - 5.09 for Escherichia coli
 - 8.10 for Listeria monocytogenes
- 3M Petrifilm
 - APC
 - Rapid APC
 - Enterobacteriaceae
 - Listeria
- For non-FDA and USDA methods, identify AOAC validation status of methods for specific surfaces

